

Creating Multimedia Products

InDesign can be used to create multimedia products that combine movie clips, sounds, images and animations into professional products that can be distributed on CD or DVD. Buttons can be used to allow the user to move to specific parts of the product.


In this chapter you will create a multimedia CD for a primary school. It will demonstrate to primary school students how to use features of the Kid Pix program which is used in many primary schools.

NOTE: Your computer system will need to be capable of importing and playing QuickTime movie clips for the activities in this chapter to be completed.

Loading the Prepared File

The screen design has been prepared for you.

- 1 Load Adobe InDesign or close the current document.
- 2 Display the FILE menu and select OPEN or click on OPEN in the OPEN A RECENT ITEM section of the START SCREEN.
- 3 Access the IDcs3 SUPPORT FILES, open the CHAPTER 13 folder and load the CHAPTER 13 file.





6 Try clicking on parts of the screen. You will notice that the yellow text frame is the only part of the screen that you can select.

- NOTE**
- i All of the other elements have been placed in a **MASTER PAGE** so that they do not interfere with the production of the page.
 - ii The blue rectangle was created in Adobe Photoshop and placed over a light blue rectangle.

Naming the Page


Each screen of the multimedia product will be a separate InDesign page. In order to set links between these pages each page should be named.



1 Select the **SELECTION TOOL** from the **TOOLS** panel and click on the yellow text frame.

- 2 Display the **WINDOW** menu, highlight **INTERACTIVE** and select **HYPERLINKS** to display the **HYPERLINKS** panel.
- 3 Click on the **PANEL MENU** icon at the top right of the panel to display the panel menu and select **NEW HYPERLINK DESTINATION**.

NOTE: You can also **RIGHT+CLICK** or **CONTROL+CLICK (Macintosh)** to display the **SHORTCUTS** menu, highlight **INTERACTIVE** and select **NEW HYPERLINK DESTINATION**.




4 Set the TYPE box to PAGE, the NAME box to FILL BUCKET and the ZOOM box to FIT IN WINDOW.

- 5 Select OK to complete the name.

Inserting a Movie Clip


A movie clip will be placed in a frame inserted inside the blue rectangle.



1 Select the RECTANGULAR FRAME TOOL from the TOOLS panel and drag a frame inside the blue rectangle so that it just fills the rectangle, but leaving a little space at the bottom.

NOTE: The space at the bottom of the rectangle is for the QuickTime movie controller bar to be displayed. This bar allows the movie to be paused and replayed.

- 2 Display the FILE menu and select PLACE (or press CTRL+D or COMMAND+D).
- 3 Access the IDcs3 SUPPORT FILES, open the CHAPTER 13 folder and load the FILL.MOV movie clip.




NOTE: On the Windows system the movie clip may not be fully displayed in the frame, but it will be when it is exported to a PFD file.

The Movie Clip Settings

When you place a movie clip in a frame the default setting is for the movie clip to only play once. This can be changed and the CONTROLLER BAR can also be turned on.

- 1 With the movie clip frame selected display the OBJECT menu, highlight INTERACTIVE and select MOVIE OPTIONS.



2 In the OPTIONS frame set the MODE to PLAY ONCE STAY OPEN so that the movie clip can be replayed.

3 Turn on SHOW CONTROLLER DURING PLAY and select OK.

NOTE: The **CONTROLLER** is the QuickTime movie bar that is placed at the base of the movie. It provides a bar that shows the progress of the movie clip and allows you to pause, restart and replay the movie clip.

4 Save the document in your STORAGE folder under the name:


Chapter 13 Kid Pix CD

NOTE: The movie clip is not saved in your document. Just a link to the movie clip's location on your network or hard disk is recorded.

Looking at the Movie Clip

Unfortunately you cannot test the playing of the movie clip in InDesign. The interactive products produced by InDesign are designed to be exported to PDF files for use in Adobe Acrobat Reader. To test the operation of the movie clip the document will need to be exported to a PDF file.


1 Display the FILE menu and select EXPORT.



2 Set the **SAVE IN** box to your **STORAGE** folder.

3 Set the **SAVE AS TYPE** or **FORMAT** box at the base of the dialogue box to **ADOBE PDF** and **FILE NAME** box to:
Kid Pix CD.PDF

4 Click on **SAVE** and the **EXPORT PDF** options dialogue box will be displayed.



5 In the OPTIONS frame set the COMPATIBILITY to ACROBAT 6 (PDF 1.5) or later.

6 Turn on OPTIMISE FOR FAST WEB VIEW and VIEW PDF AFTER EXPORTING, BOOKMARKS and HYPERLINKS.


7 Turn on NON-PRINTING OBJECTS, INTERACTIVE ELEMENTS and set the MULTIMEDIA box to USE OBJECT SETTINGS.

8 Click on EXPORT and the PDF file will be generated.

9 When the PDF file opens press CTRL+0 or COMMAND+0 to set the screen to FIT PAGE. If Acrobat Reader is not launched, load it and open the file.



10 Click on the movie clip and, if a warning message is displayed, click on PLAY.



11 The movie clip should play within the frame.